Enhancements for ZoomText 2020.200312 (March 2020)

The following items were resolved in this release. You must be logged on as an administrator to install this software.

- Resolved issue introduced in the February Update where Speech was enabled for Magnification only licenses. This update restores the speech option honoring the license indication and the speech option will remained greyed out.
- Resolved reported issues related to mouse speech when navigating text in documents.
 There were reported issues of all text being spoken as you reached the last line with the mouse pointer.
- Removed the system tray icon present when ZoomText or Fusion were running, which when clicked, disabled the magnification without warning causing problems for someone who needs magnification.
- Working with the IRS on stability issues of some internal applications running under Windows 10.

Enhancements for Fusion 2020.2003.5 and JAWS 2020.2003.13 (March 2020)

The following is a list of improvements made between the February 2020 release and the March 2020 update.

- In Office 365 and 2019, JAWS and Fusion now properly announce column and row titles
 for tables in Word documents when navigating using JAWS table reading keystrokes
 (ALT+CTRL+ARROW keys). For users who prefer to turn off reading of titles while
 navigating tables for the current document or for all documents, these options can be
 configured through JAWS Quick Settings (INSERT+V) by searching for "table" or "title."
- If the view in Outlook 365 or 2019 is set to show messages by date, JAWS and Fusion
 will now indicate using both speech and Braille the date change when you move from
 one day to the next in messages lists. For example, as you navigate a list of messages
 covering multiple days, when you move to the first message in the new date group, you
 will hear announcements such as "today," "yesterday," "last week," or "two weeks ago."
- In Microsoft Teams, addressed an issue where JAWS was not always reading as expected when navigating between messages in a conversation thread.
- Resolved an issue where Microsoft Teams would stop responding for several seconds when CTRL+BACKSPACE was pressed to delete a word in a chat edit field.
- Added a new Language Processing group, located under Text Processing in Settings
 Center. This group now contains the options for configuring language detection which
 allows JAWS and Fusion to automatically switch to the appropriate synthesizer
 language when encountering text in documents and web pages in different languages.

New England Low Vision

- In response to customer feedback, the keystroke to display the text of the current control in the JAWS Virtual Viewer so it can be selected and copied has been changed to INSERT+SHIFT+V. In Microsoft Teams, this command will also virtualize the currently selected item in a list of messages in a conversation.
- The PC Cursor is now active by default in the Weather, News, and Windows Store
 applications. Since this cursor now works much better in these apps, it is no longer
 necessary to use the Touch Cursor.
- JAWS now indicates when text on a web page is marked as deleted or inserted.
- Addressed issues with JAWS and Fusion not always reporting the correct information when navigating tables in Chrome and Edge Chromium.
- When using the ARROW keys or Navigation Quick Keys to move between controls on web pages like check boxes, resolved an issue where the visual highlight was not properly tracking the location of the Virtual Cursor.
- Addressed an issue where pressing Navigation Quick Key G to move to graphics on web
 pages was not working as expected in both the Chrome and Edge Chromium browsers.
- Addressed a customer reported issue with JAWS not identifying edit fields on certain websites in Chrome.
- If Contracted Braille input is enabled and you select all text in a document using CTRL+A, resolved an issue where using the Braille command LEFT SHIFT+D (DOTS 1-4-5) was not deleting the selected text as expected.
- Removed extra blank lines that were appearing in the JAWS Virtual Viewer when using WINDOWS Key+SEMICOLON to display comments in Word documents.
- Resolved a customer reported issue where attempting to use voice aliases to indicate attributes such as bolded text were not working when using Vocalizer Expressive.
- Resolved an issue where the emoji for a red heart was being incorrectly spoken as a black heart.
- When using the Wikipedia Research It lookup source, only the link to the article is now displayed. Due to changes with the Wikipedia website, JAWS is no longer able to retrieve the synopsis.
- You can now press INSERT+SHIFT+B in either desktop or laptop keyboard layout to obtain battery status and charging information as well as network connection status.
 You can also still use CAPS LOCK+SHIFT+B in the laptop keyboard layout to read this info.
- Added a new dictionary entry for "endnote" that is specific to the Eloquence synthesizer
 to improve this announcement for Fusion users. Other synthesizers like SAPI5 and
 Vocalizer Expressive already speak this correctly.

New England Low Vision

- Resolved a long-standing issue where configuring individual punctuation settings for a
 voice profile using the Voice Adjustment dialog box was not working properly. For
 instance, if you set the punctuation level to None for the PC Cursor voice, but leave it set
 to Most for the JAWS Cursor, Keyboard, and Tutor and Message voices, JAWS should
 now use the correct punctuation setting depending on the active voice.
- Updated the JAWS Hot Key Help (**INSERT+H**) for Skype to remove references to the Back button that existed in prior Skype versions and is now no longer available.

Download Links:

JAWS Downloads

- JAWS Connected Link: J2020.2003.13.400.exe
- JAWS Offline Installers:
 - o <u>J2020.2003.13.400-Offline-x64.exe</u>
 - o 2020.2003.13.400-Offline-x86.exe

ZoomText Downloads

- ZoomText Connected Link: ZT2020.2003.12.400.exe
- ZoomText Offline Installer: ZT2020.2003.12.400-Offline.exe

Fusion Downloads

- Fusion Connected Link: F2020.2003.5.400.exe
- Fusion Offline Installer: F2020.2003.5.400-Offline.exe

Want to Learn More About Our Products and Services

You can call our toll free number 888-211-6933 or email us at info@nelowvision.com. Our two(2) state-of-the-art technology showrooms are a wonderful resource, showcasing a variety of leading electronic low vision magnifiers and blindness products. You can schedule an appointment with one of our Vision Specialists who can help you find the right technology, training and care solution.

If you cannot come to us, our staff can even drive out and bring our Vision Store to you, for a no-obligation product demonstration. We offer a comprehensive line of products including electronic magnification low vision aids, blindness products, and leading low vision products for people with glaucoma, macular degeneration and other forms of vision loss.